

ITS Software Update Kit Instructions for Version 1.01

General

The Intelligent Terminal Software (ITS) has been updated to support several new products for the Bulletin 1395 Digital DC Drive and also the Bulletin 1396 Digital DC Drive. The purpose of this publication is to describe the steps required to install the new files.

Description

The ITS update supports the following products:

- Digital Reference Adapter Board
- RTP Adapter Board
- Bulletin 1395 firmware versions 4.01, 4.02, 4.03 and 5.01
- Bulletin 1396 Digital DC Drive
- Multi-Communication Adapter Board

Qualifications

This update is intended for use by qualified service personnel who are skilled in the use of ITS and possess basic personal computer operation skills and knowledge.

Before You Begin

The following installation procedure is intended to supplement the on-screen instructions provided during the installation. The ITS program should already be successfully installed and all preconditions met before this update is attempted. If the ITS program is not installed, or you have questions on drive or power requirements refer to the ITS Programming & Operation Manual 1300-5.13.

Installation Procedures

The disk supplied contains the update files and an installation program. The installation program can be used to automatically transfer all files from the update disk to the working disk.

Note: In order for ITS to operate correctly, the files contained on this disk must be installed using a specific directory structure. The **INSTALL** program will create the correct structure automatically.

IMPORTANT: The installation program requires the working disk to be in a different disk drive from the update disk. If this is not possible, use standard DOS functions to transfer the update files using the same directory structure as the update disk.


1. Insert the ITS update disk into a floppy drive. (we will use drive A: for this example). If you are using a drive other than A:, substitute that letter for A.
2. At the DOS prompt, type **A:** and press **ENTER**.

The DOS prompt should now be **A:\>** to indicate the current drive is the A: drive.

3. Type **INSTALL** and press **ENTER**.

At this point the **INSTALL** program main menu will appear. This menu shown in the following figure contains the choices available for installing the ITS update.

Figure 1. Installation Main Menu



4. Select program installation by pressing *I*.

IMPORTANT: The **INSTALL** program will ask you where you want the files to be installed and will suggest a possible path. The location selected **must** be the location that contains the file **ITS.EXE**.

5. Press **ENTER** to select the suggested path or enter a new directory path and then press **ENTER**.

The **INSTALL** program will now ask some questions about your computer to help set up ITS correctly. Once this information has been provided, a summary will be displayed with the option of proceeding with installation or going back and making corrections.

6. If the information displayed is correct, press *Y* to continue.

IMPORTANT: If the path entered at step 5 is correct, a warning message will appear requesting whether or not the User information should be overwritten. When installing an ITS update, **DO NOT** overwrite the User information.

NOTE: ITS maintains a list of valid users and specific information about each user including name, personal color choices, etc. If you choose to overwrite the user information the **INSTALL** program will destroy the current user list and all user information.

7. Press *N* to retain the current user list. The installation process will continue automatically.

The **INSTALL** program will copy all files to the correct directory(s). When installation is finished, a message will be displayed indicating that the installation is complete.

Update Disk Storage

Store the update disk with the ITS master disk.



ALLEN-BRADLEY
A ROCKWELL INTERNATIONAL COMPANY

With offices in major cities worldwide.

WORLD HEADQUARTERS

Allen-Bradley
1201 South Second Street
Milwaukee, WI 53204 USA
Tel: (1) 414 382-2000
Telex: 43 11 016
Fax: (1) 414 382-4444